

Element Number	Data Element Name And/ Or Description	From	Thru	Size	Elem. Char.	DATA VALUES
<u>DATA SENT TO HSMV BY CUSTOMER</u>						
1	COUNTY LOCATION CODE					
1.1	COUNTY	1	2	2	A/N	NUMERIC (RIGHT JUST)
	*** GET COUNTY FROM CONTACT ***					
1.2	AGENCY	3	4	2	A/N	NUMERIC (RIGHT JUST)
	*** GET AGENCY FROM CONTACT ***					
2	TRANSACTION TYPE	5	5	1	A/N	A, D, I
3	LICENSE PLATE NUMBER	6	15	10	A/N	CANNOT BE SPACES (LEFT JUST)
4	VEHICLE MAKE (Optional / Obsolete)	16	20	5	A/N	ALPHNUMERIC (LEFT JUST) OR SPACES
5	ADMIN STOP DATE	21	28	8	A/N	CCYYMMDD
6	STOP TYPE	29	29	1	A/N	1, 2, 3, P,T, R, SPACES
7	STOP NUMBER	30	39	10	A/N	NUMERIC (LEFT JUST) OR SPACES
8	DRIVER LICENSE NUMBER	40	52	13	A/N	ALPHNUMERIC (LEFT JUST) OR SPACES
9	FILLER	53	80	28	A/N	MUST BE SPACES
<u>DATA RETURNED TO CUSTOMER BY HSMV</u>						
1	DATA SENT TO HSMV BY CUSTOMER	1	29	29	A/N	N/A
2	STOP NUMBER	30	39	10	A/N	NUMERIC (LEFT JUST) OR SPACES
3	DRIVER LICENSE NUMBER	40	52	13	A/N	ALPHNUMERIC (LEFT JUST) OR SPACES
4	FILLER	53	69	17	A/N	SPACES
5	EDIT MASK (ERROR FLAGS)					
5.1	LOCATION CODE ERROR	70	70	1	A/N	0 OR 1
5.2	TRANSACTION TYPE ERROR	71	71	1	A/N	0 OR 1
5.3	TAG NUMBER ERROR	72	72	1	A/N	0 OR 1
5.4	VEHICLE MAKE ERROR (Optional / Obsolete)	73	73	1	A/N	0 OR 1
5.5	REPORT DATE ERROR	74	74	1	A/N	0 OR 1
5.6	STOP TYPE ERROR	75	75	1	A/N	0 OR 1
5.7	MISSING REQUIRED STOP NUMBER	76	76	1	A/N	0 OR 1
5.8	STOP NOT FOUND	77	77	1	A/N	0 OR 1
5.9	DRIVER LICENSE NOT FOUND	78	78	1	A/N	0 OR 1
5.91	STOP NOT ADDED	79	79	1	A/N	0 OR 1
6	ERROR DISPOSITION	80	80	1	A/N	E OR SPACES
<u>FIELD DESCRIPTIONS</u>						
1.1	COUNTY					DATA SENT
	01 THRU 99					
1.2	AGENCY					DATA SENT
	01 THRU 99					
2	TRANSACTION TYPE					DATA SENT
	A = ADD					
	D = DELETE					
	I = TESTING					
5	ADMIN STOP DATE					DATA SENT
	CC = CENTURY					

Element Number	Data Element Name And/ Or Description	From	Thru	Size	Elem. Char.	DATA VALUES
	YY = YEAR					
	MM = MONTH					
	DD = DATE					
6	STOP TYPE					DATA SENT
	1 = PARKING VIOLATION OBSOLETE					
	2 = TOLL VIOLATION OBSOLETE					
	3 = PARKING VIOLATION OBSOLETE					
	P = PARKING VIOLATION					
	T = TOLL VIOLATION					
	R= RED LIGHT CAMERA VIOLATION					
	SPACES = PARKING VIOLATION OBSOLETE					
7	STOP NUMBER					DATA SENT
	Stop number may only be sent with a transaction type of D or I; it is required when stop type equals R but optional for other stop types;					
8	DRIVER LICENSE NUMBER					DATA SENT
	Driver License number may only be sent with a transaction type of A or I; it is optional when stop type equals R and not allowed for other stop types;					
5	ERROR FLAGS					DATA RETURNED
	0 = NO ERROR					
	1 = ERROR					
6	ERROR DISPOSITION					DATA RETURNED
	E = ERRORS IN EDIT MASK					
	SPACES = NO ERRORS IN EDIT MASK					